



Framesoc Workbench User Guide

Generoso Pagano

**INRIA
REPORT**

December 2014

Project-Team MESCAL



Framesoc Workbench User Guide

Generoso Pagano *

Project-Team MESCAL

Inria Report — December 2014 — 17 pages

Abstract: This guide describes the Framesoc workbench. The document targets the end-users.

* INRIA, generoso.pagano@inria.fr

**RESEARCH CENTRE
GRENOBLE – RHÔNE-ALPES**

Inovallée
655 avenue de l'Europe Montbonnot
38334 Saint Ismier Cedex

Table of contents

1	Introduction	4
2	Framesoc Perspective	5
3	Management Views	6
3.1	Trace Browser	6
3.2	Trace Metadata Viewer/Editor	7
4	Analysis Views	8
4.1	Statistics Pie Chart	8
4.2	Event Density Chart	8
4.3	Event Table View	9
5	Framesoc Menu and Toolbar	11
5.1	System Initialization	11
5.2	Tool Management	13
5.3	Color Management	13
5.4	Trace Import	14
5.5	Launch Analysis Tool	14
5.6	Trace Export	15
A	Framesoc Configuration File	16

1 Introduction

Framesoc, the SoC-Trace project [1] trace management infrastructure, is composed by three main layers, as shown in Figure 1.




FIGURE 1 – Framesoc Architecture

At the lowest level, there is a Multiple-Trace database, which stores all the data concerning traces, analysis tools and the analysis result produced by the tools, using a generic data-model. Above this layer, the SoC-Trace library provides a software API to facilitate the interaction with the data-model and help the implementation of trace tools. On top of this software library, the Framesoc workbench provides a graphical user environment, facilitating trace management, basic trace analysis and tool management.

This guide describes the Framesoc workbench from the user perspective. More information about the lowest to layers of Framesoc infrastructure can be found in the technical report RT-427 [2] and the research report RR-LIG-046 [3].

2 Framesoc Perspective




FIGURE 2 – Framesoc Eclipse Workbench

The Framesoc workbench is an Eclipse application providing a perspective¹ for trace management and analysis. The Framesoc perspective (Figure 2) contains the following elements:

- A Framesoc menu (on top).
- A toolbar (the second toolbar, from the left).
- A set of views for trace management and analysis. We find on the left the two *management views*: a trace browser on top and a trace metadata viewer at the bottom. On the right there are three *analysis views*: a statistics pie chart and an event density chart on top, and an event table at the bottom.

The management views (trace browser and metadata viewer) refer to the whole system and are the entry point for trace analysis. Therefore they cannot be closed and there can be only a single instance of each of them. On the contrary, all the analysis views refer to a single trace, so they can be opened and closed as needed. For each trace, there can be an instance of each type of analysis view. The maximum number of open instances for a given type of analysis view is configurable (Appendix A). When a trace is selected in the trace browser, the corresponding metadata are shown in the metadata viewer and all the analysis view referring to that trace (if any) are highlighted. Namely, the view name is surrounded by < and >. In the example shown in Figure 2, all analysis views refer to the selected trace `scorep-mg.A.64`). On the other hand, when an analysis view is given focus, the trace shown in that view becomes the selected trace in the trace browser, so the metadata viewer is updated accordingly and all the analysis views are

1. Within an Eclipse application, a perspective defines an initial set and layout of views, menu and toolbars. The Framesoc Eclipse perspective can be activated by selecting it from the **Window > Open Perspective > Other...** menu.

consistently highlighted or unhighlighted.

The following sections describe in detail the Framesoc management and analysis views, as well as the functionalities accessible via the Framesoc menu and toolbar.

3 Management Views

3.1 Trace Browser




FIGURE 3 – Traces view

The *Traces* view (Figure 3) is the Framesoc perspective trace browser. Traces are presented in a tree viewer with a two-level hierarchy. The first level distinguishes processed traces from raw traces². Then, in each of these two categories, traces are grouped by type. The type may relate to the trace format or to the tool that created the trace. The viewer presents a trace alias for each trace.

Double-clicking on a trace opens the Event Density Chart for that trace (Subsection 4.2). Right-clicking on a single trace opens a context menu that gives access to the following functionalities:


- Show Event Density Chart: open the density chart view for this trace (see Subsection 4.2).
- Show Statistics Pie Chart: open the pie chart view for this trace (see Subsection 4.1).
- Show Event Table: open the event table view for this trace (see Subsection 4.3).
- Copy DB name to clipboard: copy to the clipboard the name of the database containing the trace raw data.
- Delete Trace: delete the trace from the system.

If more traces are selected, only the *Delete Trace* entry is displayed in this context menu. Note that if one or more traces are deleted, an update notification is sent to the other views. This allows a view to do the necessary actions if the trace it displays has been deleted.

². As described in the technical report RT-427 [2], a processed trace is a trace created by an analysis tool as the result of an analysis on another trace.

The view toolbar contains three buttons: a couple of buttons to expand/collapse the trace hierarchy and a button to manually resynchronize the displayed traces with the information contained in the Framesoc System DB (see the technical report RT-427 [2] for further details on the database architecture).

3.2 Trace Metadata Viewer/Editor



Property	Value
Tracing date	2014-03-06 09:56:38.0
Traced application	sample_video_dec
Board	pi
Operating System	linux
Number of CPUs	1
Number of events	39796
Output device	file
Description	GStreamer trace imported on C
Alias	gst_video_decoding
DB name	GSTREAMER_20140306_085
Time-unit	ns
FRAME_START_EVENT_TYPE_ID	271
NUMBER_OF_FRAMES	406

FIGURE 4 – Trace Details view

The *Trace Details* view (Figure 4) is the Framesoc perspective trace metadata viewer and editor. When a trace is open or selected in the *Traces* view, the trace metadata are displayed in a table viewer containing two columns: the property name and the property value. The different properties are grouped in two different categories: predefined properties (displayed first) and custom properties (displayed last). Those categories are identified by two different icons. The *Value* column is normally editable, with the exception of some properties that are read only (the database name and the time unit). In order to edit an editable property value, you simply have to click the value and modify it (as shown in Figure 4 for the *Board* property). When one or more values have been modified, a star (*) is displayed before the trace alias, on top of the table, and the two view toolbar buttons are enabled. The *reset* button restores all non-saved edited properties to their previous value. The *save* button stores the changes. If the *Alias* predefined property of a trace is persistently modified, other views are notified in order to take the necessary actions (e.g., update their label for the trace).

Note that if more than one trace is selected in the *Traces* view, the metadata view displays only the properties having the same name and the same value. For these properties the editing support is still working, with the note that all the selected traces metadata are modified.




FIGURE 5 – Statistics Pie Chart view

4 Analysis Views

4.1 Statistics Pie Chart

The *Statistics Pie Chart* view (Figure 5) is a Framesoc analysis view presenting several metrics in the form of a pie chart. The view is composed of two parts. On the top left, there are the metric selector and a *play* button to load the metric. At the bottom left, there is the actual pie chart. On the right, a table viewer displays the same information as the pie. This table has three columns: the pie-slice name, the percentage value and the actual value. The name column cells contain a small square icon, filled with the color corresponding to the slice. Each column header, when clicked, triggers the sorting of the rows according to the values in the corresponding column. On the top of this table, there is an editable field, acting as a filter on table rows, working on the first column (*Name*). The number of items matched by the filter, over the totality of items, is shown in the status bar under the table viewer.

For the time being, two metrics are available: the *Event Producer* instances and the *Event Type* instances. Each slice represents the number of events having a given event producer or a given type respectively.

From Figure 5 it is possible to note that there can be a special slice in the pie: the *Aggregated slice*. This slice aggregates all the slices whose value is smaller than a given threshold, being therefore difficult or impossible to see. This threshold has been empirically set to 1%, taking into account user ergonomics and screen limitations. In the table on the right, the *Aggregated slice* corresponds to a folder entry, whose sub-entries are the actual slices. All the detailed information is thus kept and available in the tabular representation.

Note that when a *Statistics Pie Chart* view is opened for a given trace using the context menu in the trace browser, no pie chart is actually displayed, since the user has to select the metric of interest first, then press the *play* button.

4.2 Event Density Chart

The *Event Density Chart* view (Figure 6) is a Framesoc analysis view displaying the event density over time in the form of a histogram. The *x* axis represents the time, while the *y* axis represents the number of events. The histogram number of bins is fixed and has been chosen in order to ensure a clear visualization, taking into account the number of pixels actually present




FIGURE 6 – Event Density Chart view

on a screen. The user can zoom and dezoom portions of the chart, using the mouse as shown in Figure 6. In particular, to zoom a portion of the chart, the user has to click to the start of the portion, drag the mouse going to the right up to the end of the portion, then release the click. To completely dezoom, the user has to do the same as above, but dragging the mouse to the left this time. Hovering the mouse on a bin, some information about the bin is displayed (the central timestamp and the number of events).

The view toolbar contains a *table* button, which triggers the visualization of the displayed portion of trace in the table view.

Note that, for the computation of the event density, all the events of the trace are considered.

4.3 Event Table View




FIGURE 7 – Events view

The *Events* view (Figure 7) is a Framesoc analysis view showing a tabular representation of trace events. The main element of this view is a table viewer, displaying a distinct row for each

event of the trace. This table has the following columns:

- Timestamp: the event timestamp.
- CPU: the number of the CPU on which the event has been produced.
- Event Producer: the name of the entity producing the event.
- Event Type: the event type name.
- Parameters: the list of the event custom parameters, with the format NAME='VALUE'.

Each column header, when clicked, triggers the sorting of the rows according to the corresponding column. The first row of the table contains an editable filter for each column. These filters accept regular expressions. For example, in Figure 7 only the events produced by a given producer are filtered. The number of events matched by the filter, over the totality of loaded events, is shown in the status bar under the table viewer.

At the bottom of the view, there is a time management bar. This bar contains a double range time slider (representing the whole trace duration) surrounded by two arrow buttons, and three more buttons on the right (*edit*, *reset* and *play* buttons). The two knobs of the double range slider identify the portion of the trace (colored in black) actually loaded in the table. This way, the user always keeps a global visibility on the whole trace, while loading only the information he is interested in. In order to change the time window loaded in the table, one needs to change the width of the black bar. However, in order to avoid spurious and useless data transfers (from disk to memory), the change is executed only when the user activates the *play* button on the right of the bar. The *reset* button resynchronizes the time bar with the time window actually loaded in the table, if they differ. In order to modify the time window visualized in the double range slider the user has several possibilities.

- Graphical selection: it is the most intuitive way and it involves using the two knobs, in order to graphically set the two bounds of the time interval.
- Time window navigation: this possibility involves using the two arrow buttons placed respectively on the left and on the right of the time bar, in order to select a time window that has the same size of the currently visualized one, but is located immediately before or immediately after the current one.
- Manual selection: by pressing the *edit* button placed immediately beside the time bar on the right, the user access a dialog (Figure 8) where it is possible to explicitly put the exact values of the time interval start and end timestamps. This dialog enables also a manual definition of the size of the time window to be used when performing the time window navigation described above.




FIGURE 8 – Time window dialog

The view toolbar contains an *adjust* button, which triggers column width resizing in order to fit the actual content.

5 Framesoc Menu and Toolbar

When the Framesoc perspective is activated, the Framesoc menu (Figure 9) and the corresponding toolbar (Figure 10) are visible.

In the menu, the different functionalities are grouped in two categories: management and trace analysis. The management menu (Figure 9a) allows the user to access system configuration, tool management and color management. The trace analysis menu (Figure 9b) allows the user to launch importers, analysis tools and exporter tools.

In the toolbar, the different buttons are simply shortcuts for the above functionalities, where corresponding icons mean corresponding functionalities. The added value of the toolbar is that, beside each of the three buttons used to launch the tools of the various category (import, analysis, export), there is a drop down menu containing the list of the tools of that category, useful to directly launch a tool.

In the following subsections, the functionalities accessible from the menu or the toolbar are explained in detail.




FIGURE 9 – Framesoc Menu



FIGURE 10 – Framesoc Toolbar

5.1 System Initialization

At system initialization, the user accesses a configuration wizard, whose first page is shown in Figure 11. This page allows the user to select the DBMS³ to be used for trace storage. In fact, as described in the technical report RT-435 [4], Framesoc can work with several DBMS. At the moment, the support has been implemented for SQLite (recommended) and MySQL.

Once the user has chosen the DBMS and pressed *Next*, he comes to the DBMS configuration page (Figure 12), which is different for each DBMS. If SQLite is selected (Figure 12a), the user has simply to enter the directory where he wants the database files to be kept. Otherwise, if MySQL is chosen (Figure 12b), the user has to specify some connection parameters (user-name, password, URL).

In both cases, after pressing *Finish*, the Framesoc storage subsystem is correctly configured. If a System DB already exists, it is reused, otherwise a new one is created. This configuration is saved in the Framesoc configuration file (Appendix A).

3. Data Base Management System






FIGURE 11 – System Initialization: DBMS selection dialog



(a) SQLite configuration dialog



(b) MySQL configuration dialog

FIGURE 12 – System Initialization: DBMS configuration

Note that after the initialization, in the case of existing System DB, if there is a mismatch between the tools registered in this System DB and the tools actually present in the Framesoc Eclipse runtime⁴, this is automatically fixed:

- If a tool exists in the DB but not in the runtime, the tool is removed with its results (if any), after user confirmation.
- If a tool exists in the runtime but not in the DB, the tool is automatically registered.

Note also that at each Framesoc startup, the system automatically checks that the storage configuration is good. If it is not the case, the system initialization wizard is automatically launched. A control for mismatch between runtime tools and System DB tools is equally done at each startup, with the same policy as described above.

4. As described in the technical report RT-435 [4] the preferred way to add tools to Framesoc is to create an Eclipse plugin, extending a specific extension point defined by Framesoc. For this reason a tool is typically a plugin in the Framesoc Eclipse runtime.

5.2 Tool Management

The tools management dialog (Figure 13) simply displays the list of tools registered to the system, enabling the installation, modification and removal of external *black-box* tools (tools that are not eclipse plugins).




FIGURE 13 – Tool manager




FIGURE 14 – Black-box tool dialog

Adding or modifying a *black-box* tool requires the user to edit the different fields of the dialog displayed in Figure 14. In particular, the user has to pick a unique tool name, specify the launching command, select the tool type (import, analysis, export), write the launching documentation.

Note that the use of external *black-box* tools is discouraged, since most of the functionalities available using Eclipse plugins are not available.

Note also that plugin tools cannot be added, edited or removed via the manage tool dialog, since they are managed as standard Eclipse plugins. Plugin tools are installed and removed using the normal Eclipse procedure (Help > Install New Software... menu).

5.3 Color Management

The color management dialog (Figure 15a) allows the user to modify the colors associated to event producers and event types in a centralized way for the whole workbench. The combo box at the top of the dialog enables the selection of the entity (event producer or event type). The list below enumerates all the entities, preceded by a small squared icon filled with the entity color.

The editable text field on top of this list can be used as a filter on the list. When an entity is selected, pressing the *edit* button gives access to the color edition dialog (Figure 15b). Pressing *OK* saves all changes. Pressing the *reset* button (under the *edit* button), reverts unsaved changes. The color configuration for a given entity is physically stored in a configuration file located in the `configuration/fr.inria.soctrace.framesoc.ui` sub-folder of the eclipse install directory. For example, the relative path to eclipse install directory of the event type color configuration file is: `configuration/fr.inria.soctrace.framesoc.ui/event_type_colors`.




FIGURE 15 – Framesoc Color Management

Note that when *OK* is pressed after changing some colors, the workbench modules are notified and the views may react by updating their colors in real-time (as done by the Pie Chart for example).

5.4 Trace Import

The trace import dialog (Figure 16) allows the user to import a new trace into the system using one of the registered importer tools. The user selects the importer from the combo box at the top, then he specifies the trace files (if more than one file is needed, all the files should be selected in the browser dialog opened when the *Browse* button is pressed). If the importer requires additional parameters (the *Doc* field normally provides this information), the user specifies these parameters too.

Finally, after pressing *OK*, the import process is launched. At the end of this process, the trace browser view is automatically updated with the new trace information.

5.5 Launch Analysis Tool

The launch analysis tool dialog (Figure 17) allows the user to launch one of the analysis tools registered to the system. The user selects the analysis tool from the combo box at the top. If the tool requires additional parameters (the *Doc* field normally provides this information), the user specifies these parameters too. Finally, after pressing *OK*, the tool is launched.




FIGURE 16 – Import trace dialog




FIGURE 17 – Launch analysis dialog

5.6 Trace Export

The trace export dialog (Figure 18) works exactly as the launch analysis tool dialog, with the difference that this time the user can launch one of the exporter tools registered to the system.




FIGURE 18 – Export trace dialog

A Framesoc Configuration File

The Framesoc configuration file (`.soctrace.conf`) is located in the user home directory. It is automatically generated and mostly configurable using the GUI.

The file contains the following parameters:

soctrace_dbms : DBMS used by Framesoc. The accepted values are: `sqlite`, `mysql`.

mysql_db_user : MySQL database user name.

mysql_db_password : MySQL database user name.

mysql_base_db_jdbc_url : MySQL database connection URL.

sqlite_db_directory : Directory containing the SQLite database files.

soctrace_db_name : Name of the Framesoc System DB.

max_view_instances : Maximum number of instances for a given type of analysis views.

References

- [1] SoC-TRACE project. <http://tinyurl.com/minalogic-soc-trace>.
- [2] Generoso Pagano and Vania Marangonzova-Martin. SoC-Trace Infrastructure. Rapport Technique RT-0427, INRIA, November 2012.
- [3] Vania Marangozova-Martin and Generoso Pagano. Gestion de traces d'exécution pour le systèmes embarqués : contenu et stockage. Research Report RR-LIG-046, LIG, Grenoble, France, 2013.
- [4] Generoso Pagano and Vania Marangozova-Martin. SoC-Trace Infrastructure Benchmark. Rapport Technique RT-0435, INRIA, June 2013.



**RESEARCH CENTRE
GRENOBLE – RHÔNE-ALPES**

Inovallée
655 avenue de l'Europe Montbonnot
38334 Saint Ismier Cedex